

1966

EC66-130 Chemicals that Control Weeds - A Guide for 1966

Follow this and additional works at: <http://digitalcommons.unl.edu/extensionhist>

"EC66-130 Chemicals that Control Weeds - A Guide for 1966" (1966). *Historical Materials from University of Nebraska-Lincoln Extension*. 3782.

<http://digitalcommons.unl.edu/extensionhist/3782>

This Article is brought to you for free and open access by the Extension at DigitalCommons@University of Nebraska - Lincoln. It has been accepted for inclusion in Historical Materials from University of Nebraska-Lincoln Extension by an authorized administrator of DigitalCommons@University of Nebraska - Lincoln.


AGRI
S
85
E7
66-130

EC 66-130

Use Pesticides Wisely



READ THE LABEL BEFORE EACH USE. Follow instructions; heed all cautions and warnings.




STORE IN ORIGINAL, LABELED CONTAINERS. Keep out of reach of children, pets, livestock and irresponsible people.



APPLY ONLY AS DIRECTED, to the crops specified, in amounts specified and at times specified. *Federal law authorizes seizure of any raw agricultural commodity moving in interstate commerce which carries a pesticide residue in excess of the established tolerance.*



DISPOSE OF EMPTY CONTAINERS SAFELY. Burn paper bags and stay out of the smoke. Destroy and bury metal and glass containers a safe distance from all water supplies.



Chemicals that Control Weeds

— a guide for 1966 —

By Weed Science Personnel

This circular deals principally with herbicides as an aid for crop production. Good farming practices including crop rotations, clean seed, adapted varieties, proper seedbed preparation, proper planting date and depth, adequate row and plant spacings, timely cultivation, and adequate fertilization are, as always, of prime importance if weed problems are to be kept to a minimum. Also, of paramount importance is the prevention of weed seed production.

This circular gives suggestions for chemical weed control based on research results at the Nebraska Agricultural Experiment Station and elsewhere.

To avoid dangers of drift, exercise judgment when spraying. Do not make field applications when wind velocity exceeds 8 mph. Wind will cause poor coverage and excessive drift. BE ESPECIALLY CAREFUL WITH 2,4-D AND SIMILAR COMPOUNDS AROUND VEGETABLES, ORNAMENTALS, TREES, SHRUBS, AND OTHER BROADLEAF CROPS.

Extension Service

University of Nebraska College of Agriculture
and Home Economics

and U. S. Department of Agriculture

Cooperating

E. F. Frolik, Dean; J. L. Adams, Director

FIELD AND VEGETABLE CROPS—PREPLANT AND PREEMERGENCE

A 13-inch band application will reduce the total herbicide used in 40-inch rows by two thirds.

Preplant treatments are made before planting the crop. Preemergence treatments are applied from planting time to just before plant emergence. Postemergence treatments are applied after emergence of weeds or crop. Weed control with preemergence treatments may be poor if there is no rain to leach the herbicide into the surface soil. To overcome dependence on rainfall and to increase dependability, preemergence herbicides should be incorporated into the surface soil with a suitable implement. Excessive rainfall may leach some of the more soluble herbicides too deeply, especially on sandy soils. Soils high in organic matter or clay content generally require more herbicide than do sandy soils for equivalent weed control. Weed control with pre-emergence herbicides is more satisfactory on surface-planted

crops and when applied to prepared seedbeds free of clods, trash, and weeds.

Some weed species are resistant to particular herbicides. Herbicides should be rotated to control a wider spectrum of weeds and to reduce the build-up of any particular herbicide in the soil. *Do not use atrazine on land that will be planted to crops other than corn or sorghum the following year—it may carry over and injure alfalfa, beans, potatoes, sugar beets, and small grains.* Herbicide residue problems in soils increase as one goes westward in Nebraska.

Sprayers should provide good agitation of spray solution and be equipped with 50-mesh or coarser screens to avoid clogging.

| Crop | Herbicide | Lb active ingredient ¹ needed/A | Apply this amount commercial product/A | Application time | Remarks |
|---|------------------|--|--|---|---|
| Castorbeans | CDAA | 5 | 25 lb Radox granules | Preemergence | Do not use on sandy soils. Incorporate with a rotary hoe. Radox controls mainly grassy weeds; Alanap-3 mainly broad-leaf weeds. Handle Radox with care to avoid irritation. |
| | NPA | 4 | 2 gal Alanap-3 | | |
| | EPTC | 2 | 1½ qt Eptam | Preplant | Immediately incorporate by double disking or equivalent soil mixing. |
| | trifluralin | 1 | 1 qt Treflan | | |
| Corn | atrazine | 2 to 3 | 2.5 to 3.75 lb Atrazine 80W | Preemergence | On sandy soil use only atrazine and at 2 lb/A. Atrazine may not control fall panicum or late emerging crabgrass. Handle Radox T with care to avoid irritation. |
| | CDAA + TCBC | 3½ + 7 | 30 lb Radox T granules | | |
| | 2,4-D ester | 1 to 1½ | 1 to 1½ qt ³ | | |
| Field beans | EPTC | 3 | 2 qt Eptam | Preplant | Immediately incorporate by double disking or equivalent soil mixing. |
| Onions | DCPA | 10 | 13.3 lb Dacthal 75W or 20 lb Dacthal 50W | Preemergence | Incorporate 1" deep at planting time. Later applications feasible if emerged weeds are destroyed prior to Dacthal application. |
| Potatoes | EPTC | 3 | 2 qt Eptam | Preplant | Incorporate immediately. |
| | DCPA | 8 to 10 | 10.6 to 13.3 lb Dacthal 75W | Preplant or Preemergence | Use lighter rate on sandy soils. Incorporation is beneficial. |
| | diphenamid | 4 | 5 lb Dymid 80W or 8 lb Enide 50W | Preplant or Preemergence | Incorporation is beneficial. |
| Sorghum (These herbicides are for central and eastern Nebraska only) | atrazine | 2 to 3 | 2½ to 3.75 lb Atrazine 80W | Preemergence | Incorporate with a rotary hoe. Do not use on sandy soils or soils low in organic matter. Heavy rains may leach atrazine and cause injury to sorghum. Atrazine may not control crabgrass and fall panicum; Herban may leave pigweed. |
| | atrazine + norea | 1 + 2 | 1¼ lb Atrazine 80W and 2½ lb Herban 80W | | |
| | norea | 3 | 3.75 lb Herban 80W | | |
| Soybeans | amiben | 3 | 6 qt Amiben | Preemergence | Incorporate amiben with rotary hoe. |
| | trifluralin | ¾ to 1 | ¾ to 1 qt Treflan | Preplant | Immediately incorporate by double disking or equivalent soil mixing. |
| Sugar beets | PEBC | 3 to 5 | 2 to 3½ qt Tillam | Preplant | Immediately incorporate by a hooded, power-driven incorporator to 1 to 2 inches. Use lower rate (3 lb/A) on clay soils. Tillam does not control Kochia. |
| Tomatoes | diphenamid | 4 | 5 lb Dymid 80W or 8 lb Enide 50W | Before or after seeding or after transplanting on weed-free surface | Incorporation is beneficial. |

FIELD CROPS – POSTEMERGENCE

Excellent growing conditions make weeds more susceptible to postemergence herbicides. Likewise, crops may be more subject to herbicide damage when growing rapidly. Adjust herbicide dosages downward when excellent conditions for growth are present the week prior to application and upward when ideal growth is limited by one or more factors.

| Crop | Herbicide | Lb active ingredient ¹ needed/A | Apply this amount commercial product/A | Application time | Remarks |
|-------------|-------------|--|--|---|--|
| Barley | 2,4-D amine | 1/2 to 3/4 | 1 to 1 1/2 pt ³ | 5-leaf to early boot | Do not treat winter barley in the fall. Spray field pennycress and mustards before April 15. |
| | 2,4-D ester | 1/4 to 1/2 | 1/2 to 1 pt ³ | | |
| Corn | 2,4-D amine | 1/2 to 1 | 1 to 2 pt ³ | Before corn is 18" high—over 18" use drop nozzles | Later applications may cause brittleness and stalk breakage. Use lower rate when good growing conditions exist to reduce corn injury. |
| | 2,4-D ester | 1/4 to 1/2 | 1/2 to 1 pt ³ | | |
| Flax | dalapon | 1 | 1 1/3 lb Dowpon | Before weeds are 1 1/2" tall | Dowpon (for grasses) and MCPA (for broadleaves) may be mixed. |
| | MCPA | 1/4 | 1/2 pt ³ | | |
| Oats | 2,4-D amine | 1/2 | 1 pt ³ | 6-leaf to flag leaf | Some injury may be expected at any stage with 2,4-D. |
| | MCPA | 1 | 1 qt ³ | | |
| Sorghum | 2,4-D amine | 1/2 | 1 pt ³ | During the period sorghum is 4" to 12" high | Spraying before 4" stage may inhibit root development, and spraying during the stage from 13" through early boot may inhibit head development. |
| | 2,4-D ester | 1/4 | 1/2 pt ³ | | |
| Sugar Beets | dalapon | 2 to 4 | 2.7 to 5.4 lb Dowpon | Grassy weeds less than 2" tall | For annual grasses. Use higher rate (4 lb/A) on grass taller than 2". |
| Wheat | 2,4-D amine | 1/2 to 3/4 | 1 to 1 1/2 pt ³ | 5-leaf to early boot | Do not spray winter wheat in the fall. Spray field pennycress and mustards as soon as good growing conditions occur in the spring. |
| | 2,4-D ester | 1/4 to 1/2 | 1/2 to 1 pt ³ | | |

PASTURES, RANGES, AND FORAGE CROPS

| Area or use | Herbicide | Lb active ingredient ¹ needed/A | Apply this amount commercial product/A | Application time | Remarks |
|--|------------------------------|--|---|---|---|
| Alfalfa and birdsfoot trefoil seedlings | dalapon | 2 to 3 | 2.7 to 4 lb Dowpon | 2 to 4 weeks after alfalfa emerges when grass seedlings are less than 2" tall | For annual grasses. Do not sell first year's crop or feed treated forage to dairy cows or animals being finished for slaughter. Can be mixed with 2,4-DB. |
| | 2,4-DB | 1 | 2 qt 2 lb/gal amine Butyrac or Butoxone | When weeds are small | For broadleaf weeds. Do not use treated forage for 30 days. DO NOT CONFUSE WITH 2,4-D. |
| | EPTC | 3 | 2 qt Eptam | Preplant | Immediately incorporate by double disking or equivalent soil mixing. Early legume injury may occur. |
| Cool-season grass seedlings | 2,4-D | 1/2 to 3/4 | 1 to 1 1/2 pt ³ | 2- to 4-leaf stage | For broadleaf weeds. |
| Warm-season grass seedlings | 2,4-D | 1/4 to 1/2 | 1/2 to 1 pt ³ | | |
| Warm-season grasses for seed | atrazine, diuron, or monuron | 3 | 3.75 lb Atrazine 80W, Karmex, or Telvar | Spring or fall before weed emergence | Do not use until second year after seeding. Less effective in heavy plant residues. |
| Annual or biennial broad-leaf weeds in pastures and ranges | 2,4-D | 1 | 1 qt ³ | Rosette stage in fall or when weeds are small in spring | Withhold milk cows from treated areas for 7 days after application. |
| Perennial broad-leaf weeds in pastures and ranges | 2,4-D | 1 to 2 | 1 to 2 qt ³ | At bud stage of pre-dominant weeds ² . April for dandelions | Annual treatment for 2 to 3 years may be necessary. Withhold milk cows from treated areas for seven days after application. |

¹ Refers to acid equivalent, phenol equivalent, or active material as applicable, calculated on a broadcast or total coverage basis.

² Retreatment may be necessary.

³ Calculated on the basis of 4 lb/gal of active ingredient (the chemicals in a product that are responsible for the herbicidal effects). For other formulations see conversion table on page 7.

NON-CROP AREAS

| Area or use | Herbicide | Lb active ingredient ¹ needed/A | Apply this amount commercial product/A | Application time | Remarks |
|---|-------------------------|---|---|---|---|
| Chemical mowing | paraquat | 1 | 2 qt Paraquat | Postemergence | Use enough water to insure good coverage. Add 1/2% wetting agent to spray solution. |
| Fence rows and roadsides (broad-leaf weeds) | 2,4-D | 1 | 1 qt ³ | Weed height 2 to 6 inches | Repeat treatments may be necessary. Add 2,4,5-T at 1 lb/A for wild rose and horse nettle. |
| Irrigation ditchbanks | diuron or monuron | 8 | 10 lb Karmex or Telvar | Soon after ditches are open. Treat before weeds appear or soon thereafter | Use enough water to insure good coverage. Use 50 mesh or coarser screens. Agitation required. |
| | atrazine or simazine | 6 | 7 1/2 lb Atrazine 80W or Simazine 80W | | |
| Soil sterilant for drives, storage areas, industrial sites, parking lots, fence lines, etc. | atrazine or simazine | 10 | 12.5 lb Atrazine 80W or Simazine 80W | Follow manufacturer's recommendations | Complete control of annuals, biennials, and most perennials. Consider possible damage to nearby trees, shrubs, grass, crops, and possible movement of sterilant with water and wind before herbicides are leached into the soil. Granular formulations generally available. |
| | bromacil | 5 | 6 1/4 lb Hyvar X | | |
| | diuron or monuron | 10 to 20 | 12.5 to 25 lb Telvar or Karmex | | |
| | erbon | 40 to 80 | 10 to 20 gal Novon concentrate or Baron | | |
| | monuron-TCA | 5 | 1 lb Urox per sq rd | | |
| | prometone | 5 | 2 1/2 gal Prometone | | |
| | Mixtures borate-monuron | | Ureabor | | |
| | bromacil plus others | | No. of mixtures | | |
| | chlorate-borate | Follow manufacturer's recommendations. | Polybor-chlorate, Chlorax, and Atlacide | | |
| | chlorate-borate-monuron | | Chlorea and Monobor-chlorate | | |
| | simazine-amitrole | | Amizine | | |
| | silvex-dalapon | | Garlon | Early weed growth | |

LAWN AND TURF WEEDS

| Weed | Herbicide | Lb active ingredient ¹ needed/A | Apply this amount commercial product/A | Application time | Remarks |
|--|---------------------------------|---|--|--|--|
| Broadleaf weeds such as dandelion, ragweed, field bindweed, and plantain | 2,4-D amine, dicamba, or silvex | 1 | 1 1/2 tbs ³ /1000 sq ft 2,4-D, Banvel D, or Silvex (Use enough water to insure good coverage) | Fall or spring (Do not spray from May 1 to Sept. 15) | AVOID drift on desirable broadleaves. DO NOT use ester formulations of 2,4-D as damaging fumes drift unpredictable distances. Spray when calm. Check with neighbors before spraying. Avoid spraying dicamba around flowers, shrubs, and trees. |
| Chickweed, henbit, violets, and knotweed | dicamba or silvex | 1 | 1 1/2 tbs ³ /1000 sq ft Banvel D or Silvex | Fall or spring (Do not spray from May 1 to Sept. 15) | Use enough water to insure good coverage. Avoid spraying dicamba around flowers, shrubs, and trees. |
| Crabgrass, foxtail, and other annual grasses | DCPA or DMPA | Follow manufacturer's recommendations with Dacthal and Zytron | | Preemergence to weeds in the spring | Use only on established grass. Rake lawn prior to application and water in. |
| Crabgrass | AMA or DMA | Follow manufacturer's recommendations with these organic arsenics | | Postemergence | POISONOUS. Repeat treatment every 7 days for 2 or 3 applications. Also effective on foxtail. May temporarily discolor bluegrass. |
| | kerosene | | 1 qt/100 sq ft | Postemergence, 2 to 4 leaves on crabgrass | Use white kerosene. Do not dilute. Apply when temperature is below 90° F. |
| | PMA | | 3 oz of 10% material/1000 sq ft | Postemergence, 2 to 4 leaves on crabgrass | POISONOUS. Repeat treatment every 7 days for 3 applications. Also controls certain diseases. Injurious to Merion bluegrass. |

| Weed | Herbicide | Lb active ingredient ¹ needed/A | Apply this amount commercial product/A | Application time | Remarks |
|-----------------------|-----------------------------------|--|--|--|--|
| Nimblewill | DMPA | Follow label recommendations on liquid Zytron container | | When growing vigorously in June and July | Thoroughly wet all plants. Re- peat applications 3 times at in- tervals of 7 to 10 days. |
| Smooth brome grass | dicamba | 2 | 3 tbs ³ Banvel D/1000 sq ft | Fall or spring (Do not spray from May 1 to Sept. 15) | Thoroughly wet all plants. Re- peat treatments may be needed. Avoid spraying dicamba around shrubs, flowers, and trees. |
| White clover | dicamba, silvex, or 2,4-5-T | 1 | 1½ tbs ³ /1000 sq ft Banvel D, Silvex, or 2,4,5-T | | |

TRoublesome Weeds and Woody Plants

Follow-up Treatments Are Necessary To Kill Escaped Established Plants And New Seedlings

| Weed | Herbicide | Lb active ingredient ¹ needed/A | Apply this amount commercial product/A | Application time | Remarks |
|---|---|---|--|---|---|
| Buckbrush (wolfberry) | 2,4-D ester | 1 to 2 | 1 to 2 qt ³ | Full foliage ² (May 10 to 25) | Use sufficient water to insure good coverage. |
| Canada thistle | 2,4-D | 2 | 2 qt ³ | Fall (rosette) and spring (early bud) ² | Same as for field bindweed. |
| | picloram | 2 | 1 gal Tordon 22K | Fall or spring on vigorous growth ² | Do not disturb for 1 to 2 weeks after treatment. |
| | 2,3,6-TBA and PBA as listed for field bindweed control. | | | | Do not use in wet areas. |
| Cottonwood, willows, and Chinese elm | 2,4-D ester | 2 to 3 | 2 to 3 qt ³ | Full foliage ² (early June) | Aerial equipment: at least 5 gal carrier/A. Annual treatment for 2 to 3 years may be necessary. Basal treatment: 2 qt of herbi- cide/10 gal of diesel. Spray tree trunk to point of run-off. |
| Downy brome | atrazine | 2 | 2.5 lb Atrazine 80W | Preemergence (fall or spring prior to April 1) | Use only in waste areas such as fence rows and ditchbanks. Do not use on cropland. Use suffi- cient water to insure good cov- erage. |
| | atrazine+amitrole monuron+amitrole | 1+½ 1+½ | 1.25 lb Atrazine 80W or Telvar plus 1 lb of Amino Tria- zole or Weedazol | Postemergence in spring prior to April 10 | |
| | Field bindweed | 2,4-D | 1 | 1 qt ³ | |
| | picloram | 2 | 1 gal Tordon 22K | Fall or spring on vigorous growth ² | Do not disturb for 1 to 2 weeks after treatment. |
| | fenac | 20 | 5/8 pt/sq rd | Fall or spring ² | Do not disturb except for shallow incorporation. Fall ap- plication more effective. High summer temperatures reduce ef- fectiveness. Follow up treat- ments with 2,4-D applications on seedlings and escapes. |
| | PBA | 40 | 10 gal/A or ½ pt/sq rd of 4 lb/gal poly- chlorobenzoic acid | | |
| | 2,3,6-TBA | 20 | 1½ lb/sq rd Granular TBA or ½ pt/sq rd Benzac 1281, Trysben 200, Tritac, or TBP | | |
| Franseria, bur and woollyleaf (Bur ragweed) | 2,4-D | 2 | 2 qt ³ emulsifiable formulations | During June ² | Same as for field bindweed ex- cept amine formulations less effective. If soil moisture con- ditions are poor, use oil-water emulsions as a carrier. |
| | picloram | 2 | 1 gal Tordon 22K | Fall or spring on vigorous growth ² | Do not disturb for 1 to 2 weeks after treatment. |
| | 2,3,6-TBA and PBA as listed for field bindweed. | | | | |

¹ Refers to acid equivalent, phenol equivalent, or active material as applicable, calculated on a broadcast or total coverage basis.

² Retreatment may be necessary.

³ Calculated on the basis of 4 lb/gal active ingredient (the chemicals in a product that are responsible for the herbicidal effects). For other formulations see conversion table on page 7.

| Weed | Herbicide | Lb active ingredient ¹ needed/A | Apply this amount commercial product/A | Application time | Remarks |
|---------------------------------|--|---|---|---|--|
| Hoary cress | 2,4-D | 2 to 4 | 1/2 to 1 gal ³ emulsifiable formulations | Rosette stage in the fall or early bud in spring ² | Same as for field bindweed ex- cept amine formulations less effective. |
| | 2,3,6-TBA and PBA as listed for field bindweed control. | | | | |
| Indian hemp (Dogbane) | 2,4-D ester | 1 | 1 qt ³ | Bud stage ² | Use lower rates in crops. |
| Johnsongrass | dalapon | 5 | 6 3/4 lb Dowpon | 8 to 12" new growth or regrowth ² | Repeat treatment 3 times, 10 to 20 days apart. |
| | TCA | 80 | 100 lb Sodium TCA | Early spring ² | Use enough water to insure good coverage. Retreat escaped plants. |
| Leafy spurge | 2,4-D | 2 | 2 qt ³ emulsifiable formulations | Early bud stage in spring or late fall ² | Same as for field bindweed ex- cept amine formulations less effective. |
| | dicamba | 10 | 2 oz Banvel D/sq rd | Fall or spring ² | Same as for 2,3,6-TBA. |
| | fenac | 16 | 1/2 pt Fenac/sq rd | Fall or spring ² | Same as for 2,3,6-TBA. |
| | picloram | 2 | 1 gal Tordon 22K | Fall or spring on vigorous growth ² | Do not disturb for 1 to 2 weeks after treatment. |
| | 2,3,6-TBA and PBA as listed for field bindweed control. | | | | |
| Milkweed, common | amitrole | 4 | 8 lb Amino Triazole or Weedazol | } Bud to bloom stage ² | Use enough water to insure good coverage. |
| | picloram | 2 | 1 gal Tordon 22K | | |
| Musk thistle | 2,4-D | 1 | 1 qt ³ | Late fall treatment of rosettes or spring before flower- ing stalks lengthen | Chemicals other than 2,4-D not necessary for effective control. Annual treatments may be nec- essary for control of new seed- lings. |
| Poison ivy | amitrole | | 2 tbs Amino Tri- azole or Weedazol/ gal water | } Full foliage (June) ² | Thoroughly wet all vegetation. |
| | AMS | | 3/4 lb Ammate X/gal of water | | |
| | 2,4,5-T or 2,4-D+2,4,5-T | | 2 tbs ³ per gal of water | | |
| Puncture vine | 2,4-D ester | 1 | 1 qt ³ | Pre-bud stage most effective | Mature burs not affected by 2,4-D. |
| Ragweed | 2,4-D | 1 | 1 qt ³ | Early summer ² | Follow-up treatments may be necessary. |
| Russian knapweed | 2,4-D | 2 | 2 qt ³ emulsifiable formulations | Early bud stage ² | Same as for field bindweed except amine formulations less effective. |
| | picloram | 2 | 1 gal Tordon 22K | Fall or spring on vigorous growth ² | Do not disturb for 1 to 2 weeks after treatment. |
| | 2,3,6-TBA, fenac, and PBA as suggested for field bindweed. | | | | |
| Russian olive | 2,4-D+2,4,5-T | 1+1 | 2 qt ³ | Full foliage ² (early June) | Same as for cottonwood. |
| Sagebrush (sand or green) | 2,4-D ester | 1 | 1 qt ³ | 4 to 8 inches new growth (June) ² | Same as for buckbrush. |
| Shattercane | EPTC | 3 | 2 qt Eptam | 10 days prior to corn planting | } Incorporate immediately by dou- ble disking or equivalent soil mixing. Some crop injury may result from Eptam or Treflan. Plant corn on the land the year following Simazine treatment. |
| | simazine | 4 | 5 lb Simazine 80W | Preplant to corn | |
| | trifluralin | 1 1/2 | 1 1/2 qt Treflan | Preplant on soybeans | |
| Swamp smartweed (Tanweed) | 2,4-D ester | 1 | 1 qt ³ | When growing vigorously ² | Controls top growth principally. Repeat treatment necessary. |
| | picloram | 2 | 1 gal Tordon 22K | Fall or spring on vigorous growth ² | Do not disturb for 1 to 2 weeks after treatment. |
| Wild rose | 2,4,5-T | 1 to 2 | 1 to 2 qt ³ | Late spring or early summer ² | Follow-up treatments may be necessary. |
| Yucca | silvex | 2 | 2 qt ³ | June ² | Use diesel as a carrier. |

TREES AND SHRUBS

Herbicides are an effective and efficient way of controlling weeds in tree and shrub plantations and in nursery line-out beds. Herbicides listed are capable of causing tree injury. However, they can be used safely. Rates of application should be strictly observed. Herbicides are recommended for control of weeds near the trees where machine cultivation is difficult or impossible. They may be applied as a circular band around the tree trunk or in bands along the tree row. A 40-inch band, 20 inches on either side of the tree row, has proved satisfactory in row plantations. Conventional machine cultivation or mowing should be used to control weeds between the rows.

Preemergence herbicides rely on moisture in the form of precipitation or sprinkler irrigation to incorporate the herbicide into the soil surface for effective weed control. Tree injury is sometimes experienced on sandy soils or those low in organic matter if heavy rainfall occurs shortly after herbicide application. The minimum herbicide rate listed is recommended for sandy soils.

Herbicides should be applied only after the trees are planted. For most of the preemergence herbicides listed here, only one application at the beginning of the growing season is recommended. Granular formulations of herbicides generally are not as satisfactory as spray formulations. In new plantations the soil should be firmly packed around the trees and free of clods and surface irregularities. A depression along the tree row caused by a mechanical tree planter may result in a dangerous concentration of chemical near the tree after a heavy rain.

ORCHARDS

| Crop | Herbicide | Lb active ingredient ¹ needed/A | Apply this amount commercial product/A | Application time | Remarks |
|-------------------------------------|-----------|---|--|------------------------------------|---|
| Apples, peaches, and pears | dalapon | 1 lb Dowpon in 15 gal water used as a wetting spray | | Postemergence, grass 1 to 10" tall | Grass control only. Use only on trees over 4 years old. KEEP SPRAY OFF TREE FOLIAGE. |
| Apples, pears, cherries, and grapes | simazine | 2 to 4 | 2.5 to 5 lb Simazine 80W | Preemergence to weeds | Use lighter rate (2 lb/A) on sandy soils. Apply a 20" band on each side of tree row. Use on trees established 1 or more years. Use only on grapes 3 years or older. |

WINDBREAKS, CONIFERS, FOREST PLANTATIONS, ORNAMENTALS, AND NURSERY LINERS

| Crop or use | Herbicide | Lb active ingredient ¹ needed/A | Apply this amount commercial product/A | Application time | Remarks |
|---------------------------------------|------------|---|--|------------------------------------|---|
| Trees | dalapon | 1 lb Dowpon in 15 gal water used as a wetting spray | | Postemergence, grass 1 to 10" tall | Grass control only. Use only on trees established 1 or more years. KEEP SPRAY OFF TREE FOLIAGE. |
| Trees | paraquat | 1/2 to 1 | 1 to 2 qt Paraquat | Postemergence | A non-selective contact herbicide. Use sufficient water and wetting agent to cover weed foliage. KEEP SPRAY OFF TREE FOLIAGE. |
| Conifers, honey locust, and green ash | diuron | 2 to 4 | 2.5 to 5 lb Karmex | Preemergence to weeds | Use lighter rate on sandy soils. Apply a 20" band on each side of tree row after trees are planted. Some injury to trees may result if soils are low in organic matter. |
| Trees and shrubs | simazine | 2 to 4 | 2.5 to 5 lb Simazine 80W | | |
| | diphenamid | 4 to 6 | 5 to 7 1/2 lb of Dymid 80W | | |

CONVERSION TABLE

| Pounds of active ingredient per gal of commercial product | Pints of commercial product needed per acre to give the following pounds of herbicide per acre | | |
|---|--|--------|-------|
| | 1/4 lb | 1/2 lb | 1 lb |
| 2.00 | 1 | 2 | 4 |
| 2.64 | 3/4 | 1 1/2 | 3 |
| 3.00 | 2/3 | 1 1/3 | 2 2/3 |
| 3.34 | 3/5 | 1 1/5 | 2 2/5 |
| 4.00 | 1/2 | 1 | 2 |
| 6.00 | 1/3 | 2/3 | 1 1/3 |

¹ Refers to acid equivalent, phenol equivalent, or active material as applicable, calculated on a broadcast or total coverage basis.

² Retreatment may be necessary.

³ Calculated on the basis of 4 lb/gal of active ingredient (the chemicals in a product that are responsible for the herbicidal effects). For other formulations see conversion table above.

CALIBRATION OF EQUIPMENT

Calibrate equipment before using to make sure that it will apply the desired amount of herbicide solution per acre. Thoroughly clean and check equipment to see that all parts are working. Select the speed at which the equipment is to be operated and drive around in the field to be sure that everything is working properly. Calibrate on ground that has the same compaction as ground on which the equipment will be used. Final sprayer calibration should be made with spray solution. Thoroughly clean all equipment immediately after use.

Sprayers

The number of gallons per acre a sprayer will discharge depends upon the ground speed, nozzle pressure, spacing of the nozzles, and size of nozzle opening (orifice). Herbicide formulations, spray carrier, and temperatures also affect spray discharge. The use of 110° nozzle tips will allow spraying closer to the ground and thereby reduce spray drift. Wettable powders will settle out if allowed to remain in spray tank without continuous agitation.

Calibrating Broadcast Type Sprayers

1. Measure the effective width of the boom in feet. (Number of nozzles times the spacing between any two adjacent nozzles.)
2. Set fan type nozzle height so there is a 50 percent overlap of the spray pattern or follow the manufacturer's recommendation.
3. Divide the width of the boom into 43,560 (the number of square feet in an acre) to get the number of feet of travel necessary to cover one acre.
4. Measure and stake off the number of feet you need to travel to cover one acre. (A fraction of an acre such as $\frac{1}{4}$ or $\frac{1}{2}$ can be used.)
5. Fill the supply tank and boom with clean water at the starting point to get an approximate calibration. Final calibration should be made with spray solution.
6. Spray the measured area exactly as you would in the field, using the same speed and pressure.
7. When you get to the end of the course immediately shut off the sprayer.
8. Measure carefully the number of gallons required to refill the spray tank. This is the volume of water the sprayer will deliver per acre—or fraction of acre as you determined in step 4. Final calibration should be made with spray solution.
9. Use this calibration information to determine the amount of herbicide to apply to a given volume of water in the spray tank. Assume that you determined your sprayer applies 18 gallons per acre. If you want to spray three pounds of EPTC (Eptam, 6 lb/gal) per acre, add one-half gallon of Eptam to each 17½ gallons of water in the spray tank.

Calibrating Band Sprayers

Most principles involved in broadcast sprayer calibration also apply to band applicators. For band spray applications use "E" type orifice tips. They deliver the same amount of spray material over the entire width of the spray pattern.

With 40" row spacing on a planter, 13,080 feet of row are required for one acre. Traveling a distance of 327 feet with a 4-row planter is one-tenth of an acre ($327 \times 4 = 1308$).

Begin band sprayer calibration by attaching plastic bags or other containers to each nozzle to catch its output. Assume your equipment is 4-row, you travel 327 feet and collect a total of one gallon of water from the four nozzles. The one gallon represents an application of one-tenth of an acre; therefore your sprayer is applying 10 gallons per acre. Now determine the fraction of the total land area you will spray with your band treatment. A 10" band on 40" spaced rows covers $\frac{1}{4}$ of the total land area; a 10" band on 30" rows covers $\frac{1}{3}$ of the total land area; a 13" band on 40" rows covers approximately $\frac{1}{3}$ of the total land area.

The amount of land area you are covering with your band spray determines the amount of chemical to use. Assume you are using amiben (2 pounds per gallon) at 3 pounds per acre on soybeans planted in 30" rows. Your band width is 10". You will be treating $\frac{1}{3}$ of the total land area. Your rate of application will be $\frac{1}{3}$ of three or 1 pound per acre. Since amiben is formulated 2 pounds of active ingredient per gallon, you will use $\frac{1}{2}$ gallon of chemical to obtain the 1 pound of amiben. Therefore, your mixture ratio should be 9½ gallons of water to $\frac{1}{2}$ gallon of amiben.

Granular Applicators

The calibration of band applicators for granular herbicides is similar to band spray calibration. There is one main difference—there is no adjustment of band width as this is set by the manufacturer.

Set the rate control adjustment as suggested by the manufacturer. Add granules to the hopper. Attach bags or other containers so they collect all granules discharged by the applicator. If your unit is 4-row with 40" spacing travel 327 feet (this represents one-tenth acre). Remove the collecting containers (they should all contain approximately the same amount) and carefully weigh together all the granules collected.

Assume you collected 4 ounces of granules. Your applicator is applying 4 x 10 or 40 ounces (2½ pounds) of granules. In case the rate should be increased or decreased change the rate control adjustment and recalibrate.